

## Requirements – PRSIM

	1. USAGE			
Category	Requirements			
Operating System	Microsoft® Windows 7, 64-bit SP1			
	Microsoft® Windows 10, 64-bit			
Prerequisite Software	Microsoft® Visual C++ 2017 Redistributables (x86 and x64), minimum <sup>[1]</sup>			
	Microsoft® .NET Framework 4.6.1 Full, minimum <sup>[2]</sup>			
Launching and Running	Microsoft® Windows User privileges			
Licensing	See Section 3			
Execution Permissions	The PRSIM application executable file must be whitelisted in all protection software:			
	• C:\Program Files (x86)\PRSIM\ <version>\bin\win64\PRSIM.exe</version>			
Folder Permissions	The following sub-folders will be created, and the user must have full permissions:			
	For your settings files:			
	C:\Users\Public\Documents\Manitoba Hydro International\Licensing\Settings			
	For your log files:			
	C:\Users\Public\Documents\Manitoba Hydro International\Licensing\Logs			
2.a INSTALLATION – Installer Utili	ty			
Category	Requirements			
Downloading	Internet connection			
Running	Microsoft® Windows Administrator privileges			
2.b INSTALLATION – MyUpdater				
Category	Requirements			
Installing	Microsoft® Windows Administrator privileges			
	Internet connection			
Launching	Microsoft® Windows Administrator privileges			
Launching (to Install or Update Software)	Microsoft® Windows Administrator privileges Internet connection			
•	·			
(to Install or Update Software)  Launching	Internet connection			
(to Install or Update Software)  Launching (to Uninstall Software)	Internet connection  Microsoft® Windows Administrator privileges			
(to Install or Update Software)  Launching (to Uninstall Software)  Launching	Internet connection  Microsoft® Windows Administrator privileges  Microsoft® Windows User privileges (unless otherwise specified)  Add both of the following URLs to all anti-virus/firewall whitelists:			
(to Install or Update Software)  Launching (to Uninstall Software)  Launching (to Launch Installed Software)	Internet connection  Microsoft® Windows Administrator privileges  Microsoft® Windows User privileges (unless otherwise specified)  Add both of the following URLs to all anti-virus/firewall whitelists:  • http://publisher.pscad.com:80/			
(to Install or Update Software)  Launching (to Uninstall Software)  Launching (to Launch Installed Software)	Internet connection  Microsoft® Windows Administrator privileges  Microsoft® Windows User privileges (unless otherwise specified)  Add both of the following URLs to all anti-virus/firewall whitelists:			
(to Install or Update Software)  Launching (to Uninstall Software)  Launching (to Launch Installed Software)	Internet connection  Microsoft® Windows Administrator privileges  Microsoft® Windows User privileges (unless otherwise specified)  Add both of the following URLs to all anti-virus/firewall whitelists:  • http://publisher.pscad.com:80/			
(to Install or Update Software)  Launching (to Uninstall Software)  Launching (to Launch Installed Software)  Connection to Publication Server	Internet connection  Microsoft® Windows Administrator privileges  Microsoft® Windows User privileges (unless otherwise specified)  Add both of the following URLs to all anti-virus/firewall whitelists:  • http://publisher.pscad.com:80/			



Operational Requirements	Supported on a local desktop, or remote desktop, or over virtual private network (VPN). Not guaranteed in a cloud desktop environment, but could be verified using diagnostic tools.	
Connection to the License Server	Add the following two URLs to all anti-virus/firewall whitelists:	
	<ul> <li>http://licensing.pscad.com:80/Licensing</li> </ul>	
	net.tcp://licensing.pscad.com:443/Licensing	
Activate/Release/Refresh a Certificate	Microsoft® Windows User Privileges	
	Internet connection	
Using Certificates	The following sub-folders will be created for certificates:	
	<ul> <li>Path: C:\Users\user_id\AppData\Local\Manitoba Hydro</li> <li>International\Licensing\Licenses</li> </ul>	
	<ul> <li>Required permissions: FullControl for <user_id></user_id></li> </ul>	
	The following sub-folder should already exist and will be used:	
	<ul> <li>Path: C:\ProgramData\Microsoft\Crypto\RSA\MachineKeys</li> </ul>	
	Required permissions: Read, Write for Everyone	
4. DIAGNOSTIC TOOLS		
Category	Requirements	
Viewing Log Files	Microsoft® Windows User Privileges	

## Notes

- 1. Both the 32-bit and 64-bit editions of Visual C++ Redistributables are required on Microsoft® Windows 64. If this prerequisite software is not already installed, the user will be prompted to install it when the PRSIM is installed.
- 2. If this prerequisite software is not already installed, the user will be prompted to install it when PRSIM is installed.



## **DOCUMENT TRACKING**

Rev.	Description	Date
0	Initial	14/Feb/2019
1	Correction to software naming convention	14/Aug/2019
2	Update to folder permissions in Chart 3	27/Oct/2020

Copyright © 2020 Manitoba Hydro International. All Rights Reserved.